

Rice Stand Establishment

Charles E. Wilson, Jr., Yesbi Wamishe, Gus Lorenz and Jarrod Hardke

Stand establishment is the first step to a successful rice crop. Factors that influence stand establishment include cultivar, seedling vigor, seeding method, seeding date, soil properties, seeding rate, seed treatments, environment and geographic location. Later management decisions are affected by stand density and uniformity. The goal of stand establishment is to obtain a uniform stand of healthy rice seedlings. Uniformity of emergence is important for accuracy of the DD50 program, pesticide application timing, drain timing for straighthead prevention, milling yield, irrigation termination, yield and harvest.

Seeding Rate

Seeding rates vary depending on cultivar, due to differences in seed size and/or weight. The RICESEED program is available to assist growers in determining the

correct seeding rate for different seeding dates and methods, soils, seedbed conditions and cultivars. This program is available at local county Extension offices or may be accessed online from the Cooperative Extension Service web site at <http://riceseed.uaex.edu/>.

Table 4-1 provides a list of seed weights and seeding rates needed to obtain the different number of seeds per square foot for commonly grown cultivars. Under most conditions where rice is drill-seeded, 30 seeds per square foot are adequate to obtain the optimum stand density of 10 to 20 plants per square foot for conventional varieties (or 6 to 13 seedlings per 7.5-inch drill row foot). For hybrids, 10 to 15 seeds per square foot is needed to obtain optimum stand density of 6 to 10 plants per square foot (or 4 to 6 seedlings per 7.5-inch drill row foot). Stand densities above the optimum density increase disease, plant height and lodging.

Table 4-1. Seeding rates for different seeds per square foot based on seed weight.

| Cultivar | Seed Weight† | Seeds/lb | Number of Seed/Sq. Ft. | | | | | | | | |
|----------|--------------|----------|------------------------|----|----|----|----|----|-----|-----|-----|
| | | | 10 | 15 | 20 | 25 | 30 | 35 | 40 | 45 | 50 |
| | | | Seeding Rate, lbs/A | | | | | | | | |
| Bengal | 27.4 | 16,569 | -- | -- | 53 | 66 | 79 | 92 | 105 | 118 | 131 |
| Caffey | 28.7 | 15,813 | -- | -- | 55 | 69 | 83 | 96 | 110 | 124 | 138 |
| Cheniere | 21.8 | 20,826 | -- | -- | 42 | 52 | 63 | 73 | 84 | 94 | 105 |
| CL111 | 26.0 | 17,462 | -- | -- | 50 | 62 | 75 | 87 | 100 | 112 | 125 |
| CL131 | 21.9 | 20,731 | -- | -- | 42 | 53 | 63 | 74 | 84 | 95 | 105 |
| CL142 AR | 25.9 | 17,529 | -- | -- | 50 | 62 | 75 | 87 | 99 | 112 | 124 |
| CL151 | 23.3 | 19,485 | -- | -- | 45 | 56 | 67 | 78 | 89 | 101 | 112 |
| CL152 | 20.5 | 22,190 | -- | -- | 39 | 49 | 59 | 69 | 79 | 88 | 98 |
| CL162 MS | 25.9 | 17,529 | -- | -- | 50 | 62 | 75 | 87 | 99 | 112 | 124 |
| CL261 | 24.6 | 18,455 | -- | -- | 47 | 59 | 71 | 83 | 94 | 106 | 118 |

† Grams per 1,000 grains or milligrams per seed.

(Continued)

Table 4-1. Seeding rates for different seeds per square foot based on seed weight.

| Cultivar | Seed Weight† | Seeds/lb | Number of Seed/Sq. Ft. | | | | | | | | |
|-------------|--------------|----------|------------------------|----|----|----|----|----|-----|-----|-----|
| | | | 10 | 15 | 20 | 25 | 30 | 35 | 40 | 45 | 50 |
| | | | Seeding Rate, lbs/A | | | | | | | | |
| Cocodrie | 25.6 | 17,734 | -- | -- | 49 | 61 | 74 | 86 | 98 | 111 | 123 |
| Francis | 22.8 | 19,912 | -- | -- | 44 | 55 | 66 | 77 | 88 | 98 | 109 |
| Jazzman | 25.2 | 18,016 | -- | -- | 48 | 60 | 73 | 85 | 97 | 109 | 121 |
| JES | 26.5 | 17,132 | -- | -- | 51 | 64 | 76 | 89 | 102 | 114 | 127 |
| Jupiter | 25.8 | 17,597 | -- | -- | 50 | 62 | 74 | 87 | 99 | 111 | 124 |
| Mermentau | 23.3 | 19,460 | -- | -- | 45 | 56 | 67 | 78 | 90 | 101 | 112 |
| Presidio | 24.3 | 18,683 | -- | -- | 47 | 58 | 70 | 82 | 93 | 105 | 117 |
| Rex | 27.6 | 16,449 | -- | -- | 53 | 66 | 79 | 93 | 106 | 119 | 132 |
| RT CL XL729 | 21.79 | 20,835 | 21 | 31 | 42 | -- | -- | -- | -- | -- | -- |
| RT CL XL745 | 21.70 | 20,922 | 21 | 31 | 42 | -- | -- | -- | -- | -- | -- |
| RT XL723 | 21.14 | 21,476 | 20 | 30 | 41 | -- | -- | -- | -- | -- | -- |
| RT XL753 | 20.50 | 22,146 | 20 | 30 | 39 | -- | -- | -- | -- | -- | -- |
| Roy J | 22.9 | 19,825 | -- | -- | 44 | 55 | 66 | 77 | 88 | 99 | 110 |
| Taggart | 27.4 | 16,569 | -- | -- | 53 | 66 | 79 | 92 | 105 | 118 | 131 |
| Templeton | 22.7 | 20,000 | -- | -- | 44 | 54 | 65 | 76 | 87 | 98 | 109 |
| Wells | 25.2 | 18,016 | -- | -- | 48 | 60 | 73 | 85 | 97 | 109 | 121 |

† Grams per 1,000 grains or milligrams per seed.

Below optimum stand densities are capable of producing high yields provided that plant distribution is uniform, weeds are controlled and additional nitrogen is applied to increase tillering. Most cultivars compensate for low seedling population by increasing tillering and the number of grains per panicle. Seeding rates should be increased by 10 percent for no-till seedbeds and early seeding; 20 percent for broadcast seeding, poor seedbed condition or clay soils; and 30 percent for water-seeding. In fields with a history of severe infestations of grape colaspis larvae (lespedeza worm) or fields with chronic infestations, seeding rates should be increased to help compensate or use a recommended seed treatment insecticide.

The recommended seeding rate of 30 seeds per square foot for conventional varieties is a reduction from previous recommendations. Recent studies suggest that seeding rates may be reduced by 25 percent from older recommendations and still obtain optimum yields (Table 4-2). Seeding rates as low as 67.5 pounds per acre (1.5 bushels/acre) result in grain yields and milling yields similar to those obtained with higher seeding rates. Reduced seeding rates lower the potential for sheath blight and the amount of fungicide needed on varieties such as

CL151 and CL161 by reducing the risk of excessive plant populations.

Table 4-2. Influence of seeding rate on grain yields of five rice varieties averaged across five locations in 2004 and 2005.

| Seed Rate | Grain Yield | | | |
|-----------|-------------|-------|---------|-------|
| | Bengal | CL161 | Francis | Wells |
| lbs/acre | bu/A | | | |
| 45.0 | 154 | 135 | 132 | 141 |
| 67.5 | 160 | 136 | 136 | 144 |
| 90.0 | 159 | 143 | 155 | 145 |
| 112.5 | 163 | 146 | 141 | 147 |
| 135.0 | 161 | 149 | 144 | 147 |
| LSD | 22 | | | |

Source: Runsick et al., 2006. p. 304-309. *B.R. Wells Rice Res. Studies 2005*. Ark. Agr. Exp. Sta. Res. Ser. 540.

Management Key

Use the RICESEED program to calculate optimum seeding rates for specific fields to avoid excessive plant populations. Proper calibration of drills is an important step in obtaining optimum seeding rates.

Recommended drill row widths for rice are between 4 and 10 inches. Limited research data suggests that under most conditions row widths between 4 and 10 inches can produce similar yields. However, as row width increases, the importance of uniform stand density also increases. Several studies show a trend for higher grain yields with narrower drill row spacing, thus a drill row spacing of 6 to 8 inches is ideal

Table 4-3. Influence of row spacing on grain yields of three rice varieties at three locations during 2004.

| Cultivar | Grain Yield | | | | | |
|----------|-------------|-----|-------|-----|------------|-----|
| | RREC† | | SEREC | | Lake Hogue | |
| | 7" | 10" | 7" | 10" | 7" | 10" |
| | bu/A | | | | | |
| Banks | 190 | 170 | 173 | 162 | 169 | 160 |
| Cybonnet | 169 | 150 | 128 | 125 | 175 | 166 |
| Francis | 206 | 180 | 160 | 154 | 213 | 193 |

† RREC = Rice Research and Extension Center, Stuttgart; SEREC = Southeast Research and Extension Center, Rohwer; and Lake Hogue = Poinsett County.

Source: Frizzell et al., 2006. p. 270-275. *B.R. Wells Rice Res. Studies 2005*. Ark. Agr. Exp. Sta. Res. Ser. 540.

Table 4-4. Seed spacing for calibration drills.

| Seeds/ Sq. Ft. | Seed Per Row Foot for Different Row Spacings | | | | |
|-------------------|---|----|----|----|-----|
| | 6" | 7" | 8" | 9" | 10" |
| 20 | 10 | 12 | 13 | 15 | 17 |
| 30 | 15 | 17 | 20 | 23 | 25 |
| 40 | 20 | 23 | 27 | 30 | 33 |
| 50 | 25 | 29 | 33 | 38 | 42 |
| 60 | 30 | 35 | 40 | 45 | 50 |
| 70 | 35 | 41 | 47 | 53 | 58 |
| 80 | 40 | 45 | 54 | 60 | 68 |

Table 4-5. Fungicide seed treatment products and disease control spectrum for rice†.

| Disease | Fungicide | Active Ingredient | Rate/cwt seed | Comments |
|------------------|--------------------------------|---|-------------------|--|
| Pythium diseases | Allegiance FL (formerly Apron) | metalaxyl | 0.75 - 1.5 fl oz | Apply with commercial seed-treating equipment. |
| | Apron XL LS | mefenoxam | 0.32 - 0.64 fl oz | Apply with commercial seed-treating equipment. Use higher rates for early planting or other severe disease situations. |
| | EverGol Energy | prothioconazole + penflufen + metalaxyl | 1 - 2 fl oz | Must use high rate for moderate to high seedling disease pressure. |

† Specific product labels should be consulted for use rates and precautions. Some products may be mixed to broaden the spectrum of seed protection. The highest labeled rates should be used for very early planting or other situations where seed germination and emergence may be delayed by environmental conditions. The effectiveness of most products is relatively short-lived under field conditions, providing about 2 to 3 weeks of seed protection at most. (Table continued)

(Table 4-3). However, other practical considerations should be made regarding row spacing. For example, wider row spacing is desirable on clay soils where clods may become lodged between the coulters on narrow row drills. Seeding rates do not need to be adjusted for differences in drill row widths in the 4- to 10-inch range. Table 4-4 provides the number of seed per row foot for 6- to 10-inch drill row spacing and seeding rates for drill calibration.

Seed Treatments

Seed treatments are often considered “insurance” and include fungicides, fertilizers, growth regulators and insecticides (when available). Although most seed treatments are generally inexpensive, they are not always recommended. The decision to use seed treatments should be based on planting date, tillage/planting method, cultivar, soil texture, disease problems and field history. Most seed treatments are for use only by commercial seed treaters, although a few are available as planter box treatments.

Fungicide seed treatments (Table 4-5) are generally recommended for early planting, clay soils, reduced tillage (especially no-till) or on fields that have a history of poor seedling emergence and seedling disease. Under the right conditions, fungicide seed treatments can result in a 10 to 20 percent stand increase over untreated seed. However, there may not be a yield increase since rice can compensate for thin, uniform stands by increased tillering. Fungicide seed treatments do not speed the rate of emergence like growth regulator treatments, nor do they control kernel or false smut. The use of fungicide-treated seed also does not guarantee that seedling disease will not impact stand density, especially three to four weeks

Table 4-5. Fungicide seed treatment products and disease control spectrum for rice†. (cont.)

| Disease | Fungicide | Active Ingredient | Rate/cwt seed | Comments |
|--|---------------------------|---|---------------------------------------|---|
| Rhizoctonia seedling diseases, general seed rots | RTU-Vitavax-Thiram | carboxin + thiram | 5.0 - 6.8 fl oz | Apply with commercial seed-treating equipment or use as a pour-on hopper box treatment. |
| | Maxim 4FS | fludioxonil | 0.08 - 0.16 fl oz | Apply with commercial seed-treating equipment. Use higher rate for severe disease situations. |
| | EverGol Energy | prothioconazole + penflufen + metalaxyl | 1 - 2 fl oz | Must use high rate for moderate to high seedling disease pressure. |
| Pythium, Rhizoctonia, general seed rot | RTU-Vitavax-Thiram | carboxin + thiram | 5.0 - 6.8 fl oz | Apply with commercial seed-treating equipment or use as a pour-on hopper box treatment. |
| | Allegiance FL or Apron XL | metalaxyl or mefenoxam | 0.75 - 1.5 fl oz or 0.32 - 0.64 fl oz | Apply with commercial seed-treating equipment. |
| | Apron XL LS + Maxim 4FS | mefenoxam + fludioxonil | 0.32 - 0.64 fl oz + 0.08 - 0.16 fl oz | Apply with commercial seed-treating equipment. Use higher rates for early planting or severe disease situations. |
| | Dynasty | azoxystrobin | 0.153 - 1.53 fl oz | Commercial seed treaters only. Usually sold with Apron XL and Maxim on rice to improve seedling disease control. To reduce seedborne blast, data suggests rates of Dynasty above 0.75 fl oz per cwt. The use of a seed treatment fungicide does not mean complete control of the disease later in the season and the field should still be scouted for blast disease and managed with deeper flood and foliar fungicides. May be included as part of CruiserMaxx Rice seed treatment. |
| | Trilex 2000 | trifloxystrobin + metalaxyl | 12-fl oz | See label. |
| | EverGol Energy | prothioconazole + penflufen + metalaxyl | 1 - 2 fl oz | Must use high rate for moderate to high seedling disease pressure. |

This information was current as of October 1, 2013 and applies only to Arkansas and may not be appropriate for other states or locations. The listing of any product in this publication does not imply endorsement of that product or discrimination against any other product by the University of Arkansas Division of Agriculture. *Every effort was made to ensure accuracy, but the user of any crop protection product must read and follow the most current label on the product - **The Label is the Law.** For further assistance, contact the local Cooperative Extension Service office.*

† Specific product labels should be consulted for use rates and precautions. Some products may be mixed to broaden the spectrum of seed protection. The highest labeled rates should be used for very early planting or other situations where seed germination and emergence may be delayed by environmental conditions. The effectiveness of most products is relatively short-lived under field conditions, providing about 2 to 3 weeks of seed protection at most.

after planting. Most fungicide seed treatments are specific for certain groups of fungi that may cause stand loss. Refer to MP154, *Plant Disease Control Products Handbook* (http://www.uaex.edu/Other_Areas/publications/HTML/MP-154.asp), for the latest information on fungicide seed treatments.

Recommended growth regulator seed treatments are currently limited to gibberellic acid (or GA3) products which include Release® and GibGro®. Seed treatments containing GA3 do not prevent seedling disease and

are not recommended for water-seeded rice. The use of GA3 is highly recommended for semi-dwarf rice cultivars, cultivars having poor seedling vigor, on clay soils, reduced tillage situations and early seeding dates. Use of GA3 treated seed may increase uniformity of emergence, minimize the effects of deep seed placement and speed up germination and emergence and has been well researched since 1988. Growth regulator seed treatments may be used in combination with other types of seed treatments, but always check the product labels for mixing instructions and precautions

prior to use. When treated with GA3, rice seedlings may appear tall and yellow shortly after emergence. Seedlings normally outgrow these symptoms within one or two weeks after emergence. If a stand failure occurs and a residual herbicide has been used, check the herbicide and GA3 product labels for replanting restrictions/recommendations with GA3-treated seed. For example, the Prowl herbicide label recommends that GA3-treated seed not be used to replant fields that have been treated with Prowl.

| Management Key |
|---|
| <p>Use gibberellic acid (GA3) seed treatments when the following conditions exist:</p> <ul style="list-style-type: none"> • Semi-dwarf rice cultivars • Cultivars with poor seedling vigor • Rice planted on clay soils • Reduced tillage rice production • Early-planted rice |

The use of fertilizer (i.e., Zn) seed treatments is addressed in later chapters that concern fertilization practices. Check with your local county Extension office for the most recent recommendations for use of new seed treatment products.

Insecticide seed treatments (Table 4-6) are recommended for fields with a history of grape colaspis or rice water weevil or soil types most commonly associated with these insects (silt loam for grape colaspis). Even in the absence of insect pressure, insecticide seed treatments have generally been observed to increase seedling emergence and early season vigor and can sometimes increase yield. Refer to MP144, *Insecticide Recommendations for Arkansas* (http://www.uaex.edu/Other_Areas/publications/PDF/MP144/MP-144.asp) for the latest information on insecticide seed treatments.

Seeding Date and Soil Temperatures

The daily maximum, mean and minimum soil temperatures measured at a 4-inch depth at three University of Arkansas Division of Agriculture Experiment Stations are provided in Table 4-7. Rice should be seeded in a seedbed that is conducive to good seed-to-soil contact when the daily average soil temperature at the 4-inch depth is above 60°F. Soil temperature measurements taken from Rohwer, Stuttgart and Keiser indicate that the average soil temperature at a 4-inch depth reaches 60°F about

Table 4-6. Insecticide seed treatment products and insect control spectrum for rice†.

| Insecticide | Active Ingredient | Rate/cwt seed | Comments |
|--------------------|---------------------|-----------------------------|--|
| Dermacor X-100 | chlorantraniliprole | 1.5 - 6.0 fl oz (see label) | Control of rice water weevil larvae. Suppression only of grape colaspis larvae. 24c Special Local Need label for use in water-seeded rice until June 5, 2018. See label. |
| NipsIt INSIDE 5 FS | clothianidin | 1.92 fl oz | Control of rice water weevil and grape colaspis larvae. Use only on dry-seeded rice. DO NOT spray crop with another neonicotinoids insecticide after using NipsIt INSIDE. DO NOT use near fish or crawfish farms. |
| CruiserMaxx Rice | thiamethoxam | 7.0 fl oz | Control of rice water weevil and grape colaspis larvae. DO NOT plant or sow Cruiser-treated seed by aerial application. Cruiser is NOT labeled for use in water-seeded rice. DO NOT use treated fields for aquaculture of edible fish or crustaceans. DO NOT exceed 120 lbs seed per acre. |

This information was current as of October 1, 2013 and applies only to Arkansas and may not be appropriate for other states or locations. The listing of any product in this publication does not imply endorsement of that product or discrimination against any other product by the University of Arkansas Division of Agriculture. *Every effort was made to ensure accuracy, but the user of any crop protection product must read and follow the most current label on the product - **The Label is the Law.*** For further assistance, contact the local Cooperative Extension Service office.

† Specific product labels should be consulted for use rates and precautions. Some products may be mixed to broaden the spectrum of seed protection. The highest labeled rates should be used for very early planting or other situations where seed germination and emergence may be delayed by environmental conditions. The effectiveness of most products is relatively short-lived under field conditions, providing about 2 to 3 weeks of seed protection at most.

Table 4-7. Minimum, maximum and mean undisturbed soil temperatures at a 4-inch depth for selected dates at three locations in Arkansas.

| Location | Rohwer, SEREC† | | | Stuttgart, RREC‡ | | | Keiser, NEREC† | | |
|--------------|---|-----|------|------------------|-----|------|----------------|-----|------|
| Latitude | 33.45 N | | | 34.49 N | | | 35.68 N | | |
| Soil Texture | Perry Clay | | | DeWitt Silt Loam | | | Sharkey Clay | | |
| Daily Temp. | Min | Max | Mean | Min | Max | Mean | Min | Max | Mean |
| Date | 4 inch undisturbed soil temperature, °F | | | | | | | | |
| March 15 | 50 | 57 | 54 | 46 | 56 | 51 | 44 | 54 | 49 |
| April 1 | 53 | 52 | 57 | 49 | 62 | 55 | 46 | 55 | 51 |
| April 15 | 60 | 69 | 64 | 56 | 69 | 63 | 55 | 64 | 59 |
| May 1 | 63 | 74 | 69 | 59 | 71 | 65 | 58 | 69 | 64 |
| May 15 | 69 | 75 | 72 | 66 | 79 | 72 | 64 | 81 | 73 |
| May 31 | 69 | 78 | 74 | 69 | 78 | 73 | 70 | 74 | 72 |

†Temperatures are the six-year average from 1990 to 1995.

‡Temperatures are the nine-year average from 1990 to 1998.

April 8, 11 and 16, respectively. Assuming adequate moisture for germination, rice emergence should occur within approximately 8, 14 and 20 days after seeding when 4-inch soil temperatures average 70°, 65° and 60°F, respectively (based on data from seeding date studies).

Management Key

Seeding when the average soil temperature at the 4-inch depth is above 60°F enhances uniform emergence and reduction in potential for seedling diseases.

When rice is planted early, more time is required for germination, emergence and development to the 5-leaf stage. For example, in the 2010 Rice DD50 Research and Development Studies, 20 rice cultivars seeded on March 31 required an average of 10 days from seeding to emergence and an additional 34 days to reach the 5-leaf stage for flooding (Table 4-8). In comparison, rice planted June 5 only required 7 days for emergence and an additional 22 days to reach the 5-leaf growth stage. The extended time between planting and flooding at the 5-leaf growth stage may increase production costs associated with flushing and weed control.

Specific beginning and ending seeding dates were once suggested, by cultivar, for the geographic regions of south, central and north Arkansas. However,

seeding date studies conducted during the past 10 years suggest these cultivar selection guidelines were not appropriate for late seeding. Depending on environmental conditions, cultivars with longer growing seasons may produce higher yields than very short-season cultivars when seeded late. Cultivar selection decisions for late-planted rice should be made based on cultivar performance in seeding date studies. Results from annual seeding date studies are published each year in *Rice Information Sheets* that summarize cultivar yield performance among different locations and seeding dates.

Table 4-8. General seeding, seedling emergence and flooding date information for the DD50 seeding date study in 2010 at the Rice Research and Extension Center near Stuttgart, Arkansas.

| Parameter | Seeding Date | | | |
|---------------------------------|--------------|----------|---------|---------|
| | March 31 | April 19 | May 12 | June 10 |
| Emergence date | April 10 | May 2 | May 18 | June 17 |
| Flood date | May 14 | May 26 | June 16 | July 9 |
| Days from seeding to emergence | 10 | 13 | 6 | 7 |
| Days from seeding to flooding | 44 | 37 | 35 | 29 |
| Days from emergence to flooding | 34 | 24 | 29 | 22 |

Source: : Frizzell et al., 2011. *B.R. Wells Rice Res. Studies 2012*. Ark. Agr. Exp. Sta. Res. Ser.

Management Key

Rice planted within the early window (Table 4-9) performs better than rice planted in later windows; however, there may be increased stand establishment risks in some fields planted at the earliest dates due to cool, wet soil conditions.

Seeding date studies conducted at the Rice Research and Extension Center (RREC), located near Stuttgart, Arkansas, were analyzed to predict the optimum seeding dates for central Arkansas (Table 4-9). The optimum seeding date range was defined as “seeding dates producing 95 to 100 percent yield potential.” Results suggest that the optimum time period for drill-seeded rice in most years, based solely on grain yields, in central Arkansas is March 23 to May 20 (Table 4-9). Growers must be cautioned that “risk factors” increase for very early seeding dates. These risk factors include, but are not limited to, stand reduction or failure, seedling stress and increased production costs. Management may overcome many of these risks and must be weighed against the potential benefits of early planting. For this reason, it is recommended that the optimum time for seeding rice be based on grain yield potential and management factors. Therefore, the estimated optimum seeding dates listed in Table 4-10, based on yield and management, are suggested for grower use. Relative yield, as affected by seeding date, is presented in Table 4-9 and should be used to make decisions concerning the profitability of late-seeded rice compared to alternate crops.

Specific cultivar recommendations for late-seeded rice (June seeding dates) should be made on yield performance in seeding date studies, seed availability and planned seeding date. Of the available cultivars that have been tested in seeding date studies, Bengal, Cypress, Drew, Francis and Wells are recommended for late planting. The hybrids developed by RiceTec, Inc. also perform well when planted late. Contact your local county Extension agent or refer to the Cooperative Extension Service web page for the latest planting date study yield information.

If the estimated date of 50 percent heading is after September 10 to 20, rice should not be planted since cool temperatures and possible frost may significantly

Table 4-9. Predicted relative yield potential for drill-seeded rice in central Arkansas by seeding date.

| Relative Yield Potential % | Actual Yield Potential† bu/A | Seeding Date Range†† | |
|-------------------------------|---------------------------------|----------------------|---------|
| | | Begin | Cut-off |
| 95.0-100.0‡ | 166-175 | March 23 | May 20 |
| 90.0-94.9 | 158-165 | May 21 | June 1 |
| 85.0-89.9 | 149-157 | June 2 | June 11 |
| 80.0-84.9 | 140-148 | June 11 | June 18 |
| 70.0-79.9 | 123-139 | June 19 | June 30 |

† Actual yield potential is based on a 100% relative grain yield of 175 bu/A at 12% moisture.

‡ Considered optimum seeding date based on potential grain yield and does not consider other management risks or milling yield potential.

†† Seeding date and relative yield potential are based on a quadratic relationship described by the equation % relative yield = 22.4 + 1.33x - 0.006x² (where x = Julian date or day number of year, where April 20 = day 110).

Source: Slaton et al. 1991.

Table 4-10. General suggested optimum and recommended seeding dates for south, central and north Arkansas geographic areas based on yield potential and management considerations.

| Geographic Region | Optimum† | | Recommended Absolute‡ | |
|-------------------|----------|---------|-----------------------|---------|
| | Begin | Cut-off | Begin | Cut-off |
| South | March 28 | May 20 | March 20 | June 15 |
| Central | April 1 | May 15 | March 25 | June 10 |
| North | April 10 | May 10 | April 1 | June 5 |

† Seeding during the optimum time frame does not guarantee high yields or suggest that crop failure cannot occur when rice is seeded during these times.

‡ Recommended absolute does NOT mean that a successful rice crop cannot be grown if seeded outside of the dates listed. Success may be evaluated and/or interpreted using various parameters (i.e., cropping systems, management, cash flow, field reclamation, etc.) and may differ among specific cultivars.

reduce grain yield and quality. The DD50 program, available at the county Extension office or online at <http://dd50.uaex.edu/dd50Logon.asp>, can be used to estimate heading dates for different cultivars. A range of dates for the occurrence of freezing temperatures in several geographic regions is provided in Table 4-11. Table 4-12 lists the predicted dates for Bengal, Spring and Wells, emerged on June 1, 15 and 30, to reach 50 percent heading in northeast (Clay County) and southeast (Chicot County) Arkansas. Finally, seeding date may influence certain diseases. Therefore, disease susceptibility must be considered when selecting a cultivar for early or late seeding. For example, earlier seeded rice is less likely to suffer severe damage from blast, smuts or bacterial panicle blight diseases but

Table 4-11. Expected freeze dates for several eastern Arkansas locations.

| City - County | Last Date in Spring with Temp. < 32°F† | First Date in Fall with Temp < 32°F† |
|-------------------------|--|--------------------------------------|
| Corning - Clay‡ | April 4 to April 17 | October 11 to October 25 |
| Augusta - Woodruff†† | March 29 to April 14 | October 19 to November 2 |
| Pine Bluff - Jefferson‡ | March 20 to April 3 | October 26 to November 9 |
| Crossett - Ashley‡ | April 4 to April 16 | October 22 to November 2 |

† Freeze dates were obtained from county soil surveys and are the dates for which temperatures below 32°F first or last occur in one to five out of every ten years.

‡ Time period from 1951 to 1974.

†† Time period from 1951 to 1990.

Table 4-12. Expected 50% heading dates of Bengal, Spring and Wells rice cultivars in southeast, central and northeast Arkansas for three June emergence dates.

| Emergence Date | Cultivar | Predicted 50% Heading Date† | | |
|----------------|----------|-----------------------------|----------------|--------------|
| | | Chicot County | Prairie County | Clay County |
| June 1 | Bengal | August 10 | August 13 | August 14 |
| | Spring | August 3 | August 3 | August 4 |
| | Wells | August 10 | August 14 | August 15 |
| June 15 | Bengal | August 22 | August 27 | August 27 |
| | Spring | August 15 | August 15 | August 17 |
| | Wells | August 23 | August 28 | August 28 |
| June 30 | Bengal | September 8 | September 12 | September 14 |
| | Spring | August 31 | August 31 | September 5 |
| | Wells | September 8 | September 13 | September 14 |

† Predictions are for 50% heading using the 30-year weather temperature means. Add 35 to 45 days for estimates of 20% grain moisture.

may have increased sheath blight problems compared to late-seeded rice.

Tillage and Post-Seeding Management

In Arkansas, the most common method of seeding rice is direct, dry seeding using a drill, airplane or air-flow truck. Broadcast seeding is most commonly used on clay soils or in wet years when speed of planting is important. Dry, broadcast-seeded rice is covered either by a final tillage operation or by flushing after levees are pulled. Dry seeding is practiced on about 94 percent of the Arkansas rice acreage. The remaining 6 percent is water-seeded rice.

The use of reduced tillage practices has increased in rice production over the past ten years. Reduced tillage practices may be more appropriately divided into two groups including stale seedbed (soil is tilled and floated in fall or late winter) or true no-till (rice is planted in previous crop stubble). A level seedbed free of potholes and excessive stubble or trash is desired, regardless of tillage and seeding method. A land plane or float is commonly used two times in conventional

tillage operations to help eliminate small depressions and high spots in fields. Tillage practices implemented in conventional tilled fields may include a disk, field cultivator, roller and a land plane or float. Tillage requirements differ among soil textures, previous crop and field condition after previous crop harvest. An excellent seedbed can be prepared on most sandy and silt loam soils with minimal tillage. Tillage on clay soils usually produces a cloddy seedbed that does not provide good seed-to-soil contact. Stale seedbed or no-till seeding usually improves seed-to-soil contact on clay soils. The use of a roller before or behind the drill often improves seed-to-soil contact and speeds emergence by compacting the soil. This is best illustrated by field observations seen each spring where rice first emerges in truck or tractor tire tracks. Research has shown that rolling behind drilled or broadcast-seeded rice can increase stand population (Table 4-13).

Management Key

Establish a smooth field surface that provides a good seedbed, drainage and water control.

Table 4-13. Influence of rolling behind drill on final rice stand density on a Perry clay soil at the Southeast Branch Experiment Station, located near Rohwer, Arkansas.

| Cultivar | Rolled† | Non-rolled† |
|----------|---------------------------|-------------|
| | Seedlings/ft ² | |
| Bond | 21 | 17 |
| Lemont | 21 | 16 |

† Seeding rate was 40 seed/ft² for each cultivar.

Generally, levees should be surveyed on 0.2 foot vertical intervals for proper water management. However, if a field is very flat and a single levee may contain more than 10 acres, levees should be marked on 0.1 foot intervals to facilitate flooding. Rice fields having considerable slope may require that levees be surveyed on 0.3 to 0.4 foot intervals to reduce the number of levees. Levees may be surveyed and marked before or after seeding. Surveying levees in minimum tillage and no-till systems during the fall, winter or early spring spreads out labor requirements that are typically encountered following planting operations. Levee formation may be completed with two to eight passes with a levee disk, depending on soil texture. A couple of hours for drying may be required between levee disk passes for clay soils. On clay soils using reduced tillage practices, a levee base may be pulled after surveying in fall, winter or early spring to minimize water seepage losses.

Levee “squeezers” have been widely adopted and provide some benefits over a conventional levee disk. Barrow ditches are typically not as deep, resulting in

better growth and production of rice in the barrow ditches. Levees are typically seeded on the final one to two passes with a levee disk that has a broadcast seeder. A levee gate should be installed in each levee by pushing out a section of soil in the direction of water flow. The ability to manage water is essential for all rice crop management practices. Construction of levees and gate installation should be performed as soon after planting as possible to enable flushing or flooding and to aid in stand establishment or pest management practices. Additional information on irrigation of rice will be covered in Chapter 10, Water Management.

Management Key

An accurate levee survey is critical to being able to manage water effectively and efficiently later in the season.

Rice harvest must be considered in planting and cultivar selection to ensure that rice matures over a range of dates and allows for timely harvest. Rice that is planted during a three-week period in April may mature and be ready for harvest at the same time. Rice can be planted much quicker than it can be harvested. Therefore, spread out planting dates to help spread out harvest.

Table 4-14 lists the estimated dates of 20 percent grain moisture for five cultivars that differ in maturity.

Table 4-14. Influence of emergence date on predicted dates for 20% grain moisture for five cultivars using 30-year weather norms for Stuttgart, Arkansas.

| Cultivar | Rice Emergence Date | | | | | | | |
|-----------|--|----------|----------|----------|----------|----------|----------|---------|
| | April 15 | April 25 | May 5 | May 15 | May 25 | June 5 | June 15 | June 25 |
| | Predicted Date for 20% Grain Moisture† | | | | | | | |
| Spring | Aug. 12 | Aug. 17 | Aug. 19 | Aug. 25 | Sept. 1 | Sept. 14 | Sept. 23 | Oct. 3 |
| Jefferson | Aug. 16 | Aug. 22 | Aug. 23 | Aug. 29 | Sept. 10 | Sept. 18 | Sept. 27 | Oct. 8 |
| Cocodrie | Aug. 21 | Aug. 26 | Aug. 27 | Sept. 8 | Sept. 14 | Sept. 23 | Oct. 3 | Oct. 13 |
| Wells | Aug. 23 | Aug. 28 | Aug. 29 | Sept. 9 | Sept. 16 | Sept. 25 | Oct. 4 | Oct. 15 |
| Bengal | Sept. 1 | Sept. 11 | Sept. 12 | Sept. 19 | Sept. 25 | Oct. 4 | Oct. 14 | Oct. 24 |

† Approximate date of 50% heading can be estimated by subtracting 35 days from listed date for Spring, Jefferson, Cocodrie and Wells or 45 days for Bengal.

References

- Counce, P.A. 1989. Row Spacing effects on rice yields. *Ark. Agric. Exp. Stn. Rep. Ser. 313*, Fayetteville.
- Counce, P.A. 1987. Asymptotic and parabolic yield and linear nutrient content responses to rice population density.
- Faw, W.F., and T.H. Johnston. 1975. Effect of seeding date on growth and performance of rice varieties in Arkansas. *Ark. Agric. Exp. Stn. Rep. Ser. 224*, Fayetteville.
- Faw, W.F., and T.K. Porter. 1981. Effect of seeding rate on performance of rice varieties. *Ark. Agric. Exp. Stn. Rep. Ser. 287*, Fayetteville.
- Frizzell, D.L., C.E. Wilson, Jr., R.J. Norman, N.A. Slaton, A.L. Richards, J.L. Hill, J.W. Branson, and S.K. Runsick. 2006. Influence of row spacing and seeding rate on rice grain yield. p. 270-275. In (R.J. Norman et al., (ed) *B.R. Wells Rice Research Studies 2005*. Ark. Agr. Exp. Sta. Res. Ser. 540.
- Gravois, K.A., and R.S. Helms. 1998. Seeding date effect on rough rice yield and head rice and selection for stability. *Euphytica* 102:151-159
- Jones, D.B., and G.H. Snyder. 1987. Seeding rate and row spacing effects on yield and yield components of drill-seeded rice. *Agron. J.* 79:623-626.
- Runsick, S.K., C.E. Wilson, Jr., A.L. Richards, J.W. Branson, and J.L. Hill. 2006. Influence of seeding rate on grain yield and milling yield of five rice cultivars in Arkansas. p. 304-309 In (R.J. Norman et al., (ed) *B.R. Wells Rice Research Studies 2005*. Ark. Agr. Exp. Sta. Res. Ser. 540.
- Slaton, N.A., R.S. Helms, H.M. Chaney, C.A. Stuart, and T.E. Windham. 1991. Results of the rice research verification trials, 1990. *AG94-9-91*. Univ. of Ark. Coop. Ext. Serv., Little Rock.